

ROS Framework Tutorial

Walking Module



Walking Module
– Initial Pose –

Background



1. Background

- 1) Representation of Pose
- 2) Pattern Generation
- 3) Balance Algorithm

2. Walking Module

- 1) Overview
- 2) Topic and Service List
- 3) Example



Background



1) Representation of Pose

- the walking module is using global coordinate system.
- All pose is represented x, y, z , roll, pitch, yaw.
- All unit is meter and radian.


$$\begin{aligned}
 {}^G T_O &= {}^G t_O(x, y, z) {}^G R_O(\phi_{roll}, \theta_{pitch}, \psi_{yaw}) \\
 &= t(x, y, z) R_z(\psi) R_y(\theta) R_x(\phi) \\
 &= \begin{bmatrix} c\psi c\theta & c\psi s\theta s\phi - s\psi c\phi & c\psi s\theta c\phi + s\psi s\phi & x \\ s\psi c\theta & s\psi s\theta s\phi + c\psi c\phi & s\psi s\theta c\phi - c\psi s\phi & y \\ -s\theta & c\theta s\phi & c\theta c\phi & z \\ 0 & 0 & 0 & 1 \end{bmatrix}
 \end{aligned}$$

G : Global Coordinate

O : Object Coordinate

$c\phi$: $\cos \phi$

$s\phi$: $\sin \phi$






Background



2) Pattern Generation


- COB(Center of Body) is at the middle of hip joints.
- LF(Left Foot) and RF(Right Foot) is at the middle of each feet.





3) Balance Algorithm

- The sensory feedback balance algorithm is used.
- The result of balance algorithm is ${}^{COB}T_{COB^*}$, ${}^{RF}T_{RF^*}$, ${}^{LF}T_{LF^*}$




Walking Module



Walking Module



1) Overview





Walking Module



2) Topic and Service List

	Name		Description
Topic (Publish)	/robotis/walking/status_message		The status message from walking module
Service (Server)	/robotis/walking/get_reference_step_data	req	Empty
		res	Reference Step Data
	/robotis/walking/add_step_data	req	"Auto Start" and "Step Data Array"
		res	Processing Result for Request
	/robotis/walking/walking_start	req	Empty
		res	Processing Result for Request
	/robotis/walking/remove_existing_step_data	req	Empty
		res	Processing Result for Request
	/robotis/walking/set_balance_param	req	All of Desired Balancing Parameter
		res	Processing Result for Request
	/robotis/walking/is_running	req	Empty
		res	Running or Not



3) Example

- Overview
 - User can choose 6 kinds of step data. (forward/backward, leftward/rightward, turn left/right)
 - User can turn balance on or off.




Walking Module



3) Example

Overview



Node

Motion Module

Topic

Service

Internal Data




Walking Module



3) Example

- Initial Pose
 - Before using walking control, the robot should be moved to initial pose






Walking Module



3) Example

- Set Mode
 - After move to initial pose, the motion mode of leg joints is changed to "walking control mode".






Walking Module




3) Example

- Balance On/Off





Walking Module





3) Example

- Balance On/Off

/robotis/walking/set_balance_param			
	Variable Type	Variable Name	Description
Request	BalanceParam	balance_param	All of parameter for balancing algorithm
Result	int32	result	The processing result of "balance_param" 0x00 : There is no error. 0x02 : The walking module is not enable. 0x20 : Previous request is not finished 0x40 : The time constant is zero or negative.



Walking Module



3) Example

- Balance On/Off – Balance Parameter for Floor Condition

```
##### cob_offset #####
cob_x_offset_m : -0.01
cob_y_offset_m : 0.0

##### FeedForward #####
hip_roll_swap_angle_rad : 0.008 # 0.0174532925 rad = 1 deg

##### Gain #####
#by gyro
gyro_gain : 0.8

#by imu
foot_roll_angle_gain : -1.0
foot_pitch_angle_gain : -1.0

#by ft sensor
foot_x_force_gain      : 0.1
foot_y_force_gain      : 0.1
foot_z_force_gain      : -0.02
foot_roll_torque_gain  : 0.002
foot_pitch_torque_gain : 0.0015

##### TIME CONSTANT #####
#by imu
foot_roll_angle_time_constant : 0.1
foot_pitch_angle_time_constant : 0.1

#by ft
foot_x_force_time_constant : 0.2
foot_y_force_time_constant : 0.2
foot_z_force_time_constant : 0.2
foot_roll_torque_time_constant : 0.2
foot_pitch_torque_time_constant : 0.2
```

in KINDRED
: Carpet

```
##### cob_offset #####
cob_x_offset_m : -0.01
cob_y_offset_m : 0.0

##### FeedForward #####
hip_roll_swap_angle_rad : 0.008

##### Gain #####
#by gyro
gyro_gain : 0.5

#by imu
foot_roll_angle_gain : -1.0
foot_pitch_angle_gain : -1.0

#by ft sensor
foot_x_force_gain      : 0.1
foot_y_force_gain      : 0.1
foot_z_force_gain      : -0.02
foot_roll_torque_gain  : 0.002
foot_pitch_torque_gain : 0.0015

##### TIME CONSTANT #####
#by imu
foot_roll_angle_time_constant : 0.2
foot_pitch_angle_time_constant : 0.2

#by ft
foot_x_force_time_constant : 0.2
foot_y_force_time_constant : 0.2
foot_z_force_time_constant : 0.2
foot_roll_torque_time_constant : 0.2
foot_pitch_torque_time_constant : 0.2
```

in ROBOTIS
: Hard Floor



Walking Module



3) Example

- Balance On/Off – Balance Parameter for Floor Condition

```
##### cob_offset #####
cob_x_offset_m : -0.01
cob_y_offset_m : 0.0

##### FeedForward #####
hip_roll_swap_angle_rad : 0.008 # 0.0174532925 rad = 1 deg

##### Gain #####
#by gyro
gyro_gain : 0.8

#by imu
foot_roll_angle_gain : -1.0
foot_pitch_angle_gain : -1.0

#by ft sensor
foot_x_force_gain      : 0.1
foot_y_force_gain      : 0.1
foot_z_force_gain      : -0.02
foot_roll_torque_gain  : 0.002
foot_pitch_torque_gain : 0.0015

##### TIME CONSTANT #####
#by imu
foot_roll_angle_time_constant : 0.1
foot_pitch_angle_time_constant : 0.1

#by ft
foot_x_force_time_constant : 0.2
foot_y_force_time_constant : 0.2
foot_z_force_time_constant : 0.2
foot_roll_torque_time_constant : 0.2
foot_pitch_torque_time_constant : 0.2
```

in KINDRED
: carpet

```
##### cob_offset #####
cob_x_offset_m : -0.01
cob_y_offset_m : 0.0

##### FeedForward #####
hip_roll_swap_angle_rad : 0.008

##### Gain #####
#by gyro
gyro_gain : 0.5

#by imu
foot_roll_angle_gain : -1.0
foot_pitch_angle_gain : -1.0

#by ft sensor
foot_x_force_gain      : 0.1
foot_y_force_gain      : 0.1
foot_z_force_gain      : -0.02
foot_roll_torque_gain  : 0.002
foot_pitch_torque_gain : 0.0015

##### TIME CONSTANT #####
#by imu
foot_roll_angle_time_constant : 0.2
foot_pitch_angle_time_constant : 0.2

#by ft
foot_x_force_time_constant : 0.2
foot_y_force_time_constant : 0.2
foot_z_force_time_constant : 0.2
foot_roll_torque_time_constant : 0.2
foot_pitch_torque_time_constant : 0.2
```

in ROBOTIS
: Hard Floor



3) Example

- Balance On/Off – Balance Parameter

```
##### cob_offset #####
cob_x_offset_m : -0.01
cob_y_offset_m : 0.0

##### FeedForward #####
hip_roll_swap_angle_rad : 0.008 # 0.0174532925 rad = 1 deg

##### Gain #####
#by gyro
gyro_gain : 0.8

#by imu
foot_roll_angle_gain : -1.0
foot_pitch_angle_gain : -1.0

#by ft sensor
foot_x_force_gain      : 0.1
foot_y_force_gain      : 0.1
foot_z_force_gain      : -0.02
foot_roll_torque_gain  : 0.002
foot_pitch_torque_gain : 0.0015

##### TIME CONSTANT #####
#by imu
foot_roll_angle_time_constant : 0.1
foot_pitch_angle_time_constant : 0.1

#by ft
foot_x_force_time_constant    : 0.2
foot_y_force_time_constant    : 0.2
foot_z_force_time_constant    : 0.2
foot_roll_torque_time_constant : 0.2
foot_pitch_torque_time_constant : 0.2
```


If user wants to turn off the balance algorithm, these gains should be zero.



Walking Module



3) Example






Walking Module



3) Example

- Add step data to walking module




1. adjust walking parameter

2. Click walking type, the robot will walk.



Walking Module





Walking Module



3) Example

- Add step data to walking module

/robotis/walking/add_step_data

	Variable Type	Variable Name	Description
Request	bool	auto_start	If "auto_start" is true, the robot will start walking automatically.
	bool	remove_existing_step_data	if "remove_existing_step_data" is true, all of the previous added step data are removed.
	StepData[]	step_data_array	step data array of user specified
Result	int32	result	The processing result of "add_step_data" 0x00 : There is no error. 0x02 : The walking module is not enable. 0x04 : There is some problem in step time data. 0x08 : There is some problem in step position data. 0x400 : The robot is walking now.



3) Example

- Add step data to walking module - StepData

```
#### Step Position Data
## MovingFootFlag
# LFootMove = 1;
# RFootMove = 2;
# NFootMove = 3;
int16      moving_foot

### Unit [meter, rad]
float32     foot_z_swap
float32     body_z_swap
float32     torso_yaw_angle_rad
PoseXYZRPY  left_foot_pose
PoseXYZRPY  right_foot_pose
PoseZRPY    body_pose
```

```
#### StepTimeData
## WalkingStateFlag
# InWalkingStarting = 0;
# InWalking         = 1;
# InWalkingEnding   = 2;
int16      walking_state

## Unit [sec]
float32     abs_step_time

# dsp_ratio >= 0.0 && dsp_ratio < 1.0
# recommend value is 0.2
float32     dsp_ratio
```



Walking Module



3) Example

